

香港寬頻商業寬頻服務 HKBN Business Broadband Service

互聯網連線配置及電子郵件設定指南 Internet Connection & Email Configuration Guide



<u>目錄 Table of Content</u>

- (I) 簡介 Introduction
- (II) 電腦系統基本要求 System Requirement
- (III) 如何安裝香港寬頻商業寬頻服務How to Use HKBN Business Broadband Service

視窗 98 動態 IP 位址配置指南 Installation Guide for Windows 98 Using DHCP IP Address 視窗 98 固定 IP 位址配置指南 Installation Guide for Windows 98 Using Static IP Address

- (IV) 如何設定 Internet Explorer Internet Explorer Set Up via HKBN Business Broadband
- (V) HKBN Broadband Mail POP3 用戶設定 Outlook 手冊 HKBN Broadband Mail Outlook Setup for POP3 User Guide
- (VI) 如何透過 HKBN Broadband Mail 網上電郵服務接收電子郵件 How to Check E-mail via HKBN Broadband Mail Webbased E-mail Account



(I) 簡介 Introduction

香港寬頻為配備自建設施的寬頻及多媒體服務供應商,致力為客戶提供完善先進的 寬頻互聯網方案,以及優質的客戶服務。透過最新的光纖互連大廈互聯網接駁技術, 香港寬頻商業寬頻服務為您提供可靠及相同雙向頻寬的互聯網服務。

HKBN's Business Broadband Service offers customers high-speed access to the Internet. Our Fiber-To-The-Building architecture caters for high speed and high bandwidth multimedia applications with two-way symmetric bandwidth for upload and download.

這本安裝指南能讓您簡易地使用我們為您提供的優質互聯網服務。

Simply follow the instructions with this user guide and enjoy the many benefits of our Internet access service.

(II) 電腦系統基本要求 System Requirement

香港寬頻商業寬頻服務基本安裝配備:

Basic requirements for installation of HKBN Business Broadband:

- Pentium 電腦配備 166 MHz (或以上)處理器 Pentium 166MHz Processor (or above)
- 32MB RAM 記憶體 32MB RAM memory
- 微軟視窗 95/98/2000/ME/NT4.0 SP3 Microsoft Windows 95/98/2000/ME/NT4.0 SP3
- 已安裝之以太網絡接駁卡 Pre-installed Ethernet Card



(III) 如何安裝香港寬頻商業寬頻服務 How to Use HKBN Business Broadband Service

<u>視窗 98 動態 IP 位址配置指南</u> Installation Guide for Windows 98 Using DHCP IP Address

於安裝香港寬頻商業寬頻服務前,請首先確定已安裝網路咭於電腦內,網路咭安裝 程序請參照網路咭用戶手冊。

Before installing HKBN Business Broadband Service, please ensure the network card has been properly installed in your PC according to the user manual of the network card.

於完成網路咭安裝後參照下列步驟:

Follow the steps below when the LAN card has completed installation:

1. 設定網路

Network Setting

- 1.1. 按「開始」鍵並選擇「設定」 Click "Start" and select "Settings"
- 1.2. 按「控制台」 Click "Control Panel"
- 1.3. 再按兩次「網路」 Double click "Network"
- 加裝 TCP/IP (如已加裝 TCP/IP,可直接跳至步驟三)
 Add TCP/IP (GO directly to Step 3 if TCP/IP has been installed)
 - 2.1. 按「新增」鍵 Click "Add"
 - 2.2. 選擇「通訊協定」然後按「新增」 Choose "Protocol" and then "Add"
 - 2.3. 於左欄「製造廠商」選擇「Microsoft」及於右欄「網路通訊協定」請選 「TCP/IP」,然後按「確定」 Choose "Microsoft" in "Manufacturer" on the left and "TCP/IP" in

"Network Protocols" on the right, and then click "OK".



3. Netwo

Configuration Identific.	ation Access Cont	trol	
The following network	components are in:	istalled:	
Client for Microso	ft Networks e Networks grated Fast Etherne ible Protocol	et Controller (3C9050	
Add	Remove	Properties	
Client for NetWare N	etworks		•
Eile and Print Sha Description TCP/IP is the proto wide-area networks	ring	ect to the Internet a	nd

Bindngs	Advanced	N	etBIOS
DNS Configuration	iateway WINS C	Configuration	PAdo
An IP address can b If your network dnes your network adminis the space below.	e automatically assi not automatically a trator for an addres	gned Io this o ssign IP addr s, anc then t	computer esses, a: ypeitin
Obtain an IP ac	Idress automatically	ł	
<u>S</u> pecify an IP a	ddress:		
[P Address			
Subnet Mask:		. [
	-		

- 3.1. 選擇您所安裝的網路咭的 TCP/IP Select TCP/IP of your installed network card
- 3.2. 選擇「組態」鍵 Select "Configuration" tab
- 3.3. 選擇您所安裝的網路咭所顯 示的 TCP/IP,然後按「內 容」鍵

Select TCP/IP* generated from your installed network card and click "Properties"

附圖所顯示的TCP/IP 只供參考 The TCP/IP figured in diagram is for reference only

- 4.1. 按「IP 位址」
 Select the "IP Address" tab
 4.2. 選擇「自動取得 IP 位址」
- Select "Obtain an IP address automatically"
- 4.3. 再按「確定」 Click "OK" 4.4. 按「通訊
- 閘」畫面,確定此 畫面並未填寫 Click "Gateway" and make sure the field has not been filled in



5. TCP/IP Properti

Bindngs DNS Configuration	Advanced Gateway WINS Confid	NetBIOS guration PAddres
Disable DNS		
C Erable DNS		
Host	D <u>o</u> main:	
DNS Server Sea	rch Order	
		<u>A</u> dd
	Be	mave
	<u></u>	
Doman Suffix S	earch Order —	
		Add
		move
1. 		
	r	

- 5.1. 選擇「DNS 組態」鍵 Select "DNS Configuration" tab
- 5.2. 選擇「關閉 DNS」 Select "Disable DNS"
- 5.3. 再按「確定」,並重新啟動 電腦 Click "OK" and re-start

your computer

當您完成電腦的網絡設定後,下一步請安裝

Internet Explorer Please continue to set up the Internet Explorer option after finishing the configuration of your computer's network properties.



視窗 98 固定 IP 位址配置指南

Configuration Guide for Windows 98 Using Static IP Address

在安裝香港寬頻商業寬頻服務前,請首先確定已安裝網路咭於電腦內,網路咭安裝 程序請參照網路咭用戶手冊。

Before installing HKBN Business Broadband Service, please ensure the network card has been properly installed according to the user manual of the network card.

於完成網路咭安裝後參照下列步驟:

Follow the steps below when the LAN card has completed installation:

1. 設定網路

Network Setting

- 按「開始」鍵並選擇「設定」
 Click "Start" and select "Settings"
- 1.2. 按「控制台」 Click "Control Panel"
- 1.3. 再按兩次「網路」 Double click "Network"
- 加裝 TCP/IP (如已加裝 TCP/IP,可直接跳至步驟三)
 Add TCP/IP (GO directly to Step 3 if TCP/IP has been installed)
 - 2.1. 按「新增」鍵 Click "Add"
 - 2.2. 選擇「通訊協定」然後按「新增」 Choose "Protocol" and then "Add"
 - 2.3. 於左欄「製造廠商」選擇「Microsoft」及於右欄「網路通訊協定」請選 「TCP/IP」,然後按「確定」 Choose "Microsoft" in "Manufacturer" on the left and "TCP/IP" in

"Network Protocols" on the right, and then click "OK".



3. Network

WUIK			
onfiguration Identifica	ation Access Cort	trol	
The following <u>n</u> etwork	components are in	istalled:	
Client for Microsol Client for NetWar Client for NetWar Client 3Com 3C920 Inte FIX/SPX-compati CP/IP	ft Networks e Networks grated Fast Etherne ible Protocol	et Controller ((3C905C-
Add	R <u>e</u> move	PI	operties
Client for NetWare N	etworks		•
Eile and Print Sha Description TCP/IP is the protor wide-area networks	ring	ect to the In	ternet and
wide-area hetworks.			

DNS Configuration Gateway WINS Configuration IP Address An IP address can be automatically assigned to this computer. If your network does not automatically assign IP addresses, ask your network administrator for an address, and then type it in the space below. Image: Computer State St	Bindings	Advanced		N	etBIOS
An IP address can be automatically assigned to this computer. If your network does not automatically assign IP addresses, ask your network administrator for an address, and then type it in the space below.	DNS Configuration	Gateway	WINS Config	juration	IP Addre
Obtain an IP address automatically Specify an IP address IP Address: 203.98.135.130 Subnet Mask: 255.255.255.252	An IP address can If your network doe your network admir the space below.	be automa es not autor histrator for	ically assigned natically assign an address, an	to this c IP addri d then ty	omputer. esses, ask vpe it in
IP Address: 203.98.135.130 Subnet Mask: 255.255.255.252	C <u>O</u> btain an IP	address au	omatically		
IP Address: 203.98.135.130 Subnet Mask: 255.255.255.252	Specify an IP	address			
Subnet Mask: 255.255.255.252	IP Address:	203	. 98 .135	. 1 3 0	
	S <u>u</u> bnet Masl	c 255	. 255 . 255	. 252	
		407 O L			

- 3.1. 選擇您所安裝的網路咭的 TCP/IP Select TCP/IP of your installed network card
- 3.2. 選擇「組態」鍵 Select "Configuration" tab
- **3.3.** 選擇您所安裝的網路咭所顯示的

TCP/IP,然後按「內容」鍵 Select TCP/IP generated from your installed network card and click "Properties"

附圖所顯示的TCP/IP 只供參考 The TCP/IP figured in diagram is for reference only

- 4.1. 按「IP 位址」 Select the "IP Address" tab
- 4.2. 選擇「指定 IP 位址」鍵,
 並輸入香港寬頻提供的
 「IP 位址」及「子網路遮
 罩」

Click on "Specify an IP address" and type in your ASSIGNED "IP address" and "Subnet Mask" provided by HKBN.



5. TCP/IP Propertie

ci mi riopenies				
Bindings) Adv	anced	N	etBIOS
DNS Configuration	Gateway	WINS Config	uration	IP Addre:
The first gateway The address order machines are user	n the Installe in the list wi d.	ed Gateway list Il be the order i	will be t n which	he default. these
<u>N</u> ew gateway: 203 . 98 . 1	35.129	Add		
Installed gatewa	ys: 29	<u>R</u> emov	e	
			-	Cancel

6.	TCP/IP Properties		?×
	Bindings DNS Configuration	Advanced Gateway WINS Confi	NetBIOS guration IP Address
	C Disable DNS		
	Host: NWT	D <u>o</u> main:	
	DNS Server Sear	ch Order	Add
		B	emove
	J Domain Suffix Se	arch Order —	
			Add
			2 <u>110</u> 46
		ок	Cancel

- 5.1. 按「通訊閘」
- Select the "Gateway" tab 5.2. 輸入香港寬頻提供的「通
 - 訊閘」並按「新增」 Type in your ASSIGNED "Gateway IP address" and then click the "Add" button
- 5.3. 然後按「確定」 Click "OK"

- 6.1. 按「DNS 組態」鍵 Select "DNS Configuration" tab
- 6.2. 選擇「啟動 DNS」 Select the "Enable DNS"
- 6.3. 於「主電腦」位置鍵入名 稱,在「DNS 伺服器搜尋 順

序」內,鍵入香港寬頻提供 的 DNS,然後按「新增」 Enter a host name into the "Host" column and then enter the DNS IP addresses given by HKBN, and then click "Add".



7. TCP/IP Proper

CP/IP Properties				?
Bindings	Adv	anced	Ne	etBIOS
DNS Configuration	Gateway	WINS Confi	guration	IP Addres
C Disable DNS				
• Enable DNS				
Host Mur		Domain: [
Test lines 1	_	- <u>-</u>		_
DNS Server Sea	rch Order —			
			<u>A</u> dd)	
203.98.129.1	I	B	emove	1
203.98.129.9	9			1
Demain Cuffin C	h Ouder			
Domain Sumx Se	arch Urder	_	12 W SI	
		_	Add	
		B	emove	
		OK		Cancel

7.1. 加入 DNS IP 位址後, 按 「確定」並重新啟動電腦 After added the DNS IP addresses, click "OK" and re-start your computer

當您完成電腦的網絡設定後,下一步請安裝

Internet Explorer Please continue to set up the Internet Explorer option after finishing the configuration of your computer's network properties.



(IV) 如何設定 Internet Explorer Internet Explorer Set Up via HKBN Business Broadband

1. 設定首頁

Configure home page

- 按「開始」及選擇「設定」
 Click "Start" and select "Settings"
- 1.2. 再按「控制台」 Click "Control Panel"
- 1.3. 按兩次「Internet 選項」 Double click "Internet Options"
- 1.4. 選擇「一般」鍵 Select "General" tab
- 1.5. 在網址一欄輸入 http://hkbnes.net Enter http://hkbnes.net in the "address" field of "Homepage" Section

1.6. 按「確定」 Click "OK" to confirm

2. Internet Options

Use the Connection Wizard Io conn computer to the Internet.	ect your Setur
My Connection (Default)	Add.
	<u> </u>
	<u>S</u> ettin <u>c</u> s
Diel whenever a network connection is Always dial my default connection Current default My Connection Eleform system security check before d	not present
LAN settings	LAN Setting:

- 2.1. 選擇「連線」 Select "Connection" tab
- 2.2. 按「區域網路設定」 Click "LAN Settings"



use o	if manual :	seltings, disable	e automatic configu	ration.
	utcmatica	Illy detect settin	gs	
ΓU	se autom	atic configuratio	on <u>s</u> cript	
A	ddjess 🛛			
Proxy	server			
ΠŪ	se a pro <u>x</u> i	y server		
A	ddiess: [ftrsproxy	Port: 80	Advan <u>c</u> e
F	Bunass	now server fo	r local addresses	

4. 然後重新啟動 Internet Explorer Restart the Internet Explorer

- 3.1. 在「區域網路設定」內選擇 「自動偵測設定」
 Select "Automatically detect settings" in "Local Area Network (LAN) Settings"
- 3.2. 按「確定」 Click "OK"



(V) HKBN Broadband Mail POP3 用戶設定 Outlook 手冊 HKBN Broadband Mail Outlook Setup for POP3 User Guide

1. 開啟 Microsoft Outlook / Outlook Express Start Microsoft Outlook / Outlook Express

A3 Mol	Nemi Directory Se	rvice	<u>600</u>
Account	Туре	Connection	111 111
			Disc
			The extent
			Incid
			(Date
			1
			58884

Your Hame	
Wien you send ensial, Type your name as you	your name will appear in the Fron fidd of the outgoing nessag would like it to appear.
Display name:	Torni For example John Smith
	. Cadi Besta Ca



- 2.1. 在工具列打開「工具」並選 擇「帳號」
 Click on pull-down menu "Tools", then select "Accounts".
- 2.2. 在「Internet 帳號」選擇「新 增」並選擇「郵件」
 Click on "Internet Accounts" tab and then click the "Add" button and select "Mail".
- 3.1. 在「顯示名稱」一欄輸入您的名稱,此名稱將會在送出的郵件中寄件者一欄出現。 然後按「下一步」

Enter your "Display Name" and press "Next". This name will be displayed as "Sender" in all outgoing mails.

4.1. 在「電子郵件地址」選擇 「我要使用現有的電子郵件 地址」,並在「電子郵件地 址」填上你的個人電子郵件 地址 (Email Address),然後 按「下一步」
Select "I already have an email address that I'd like to use" under Internet

Connection Wizard and then Enter your email address and press "Next".



Ay ecoloring mail general	e a POP3	· bervel	ų.	
noming mail (FOP). 114	AP or HTTP1 and			
pop3.gigalirkmail.com	1			
to SMTP server is the se	everthatic used	For your pulgai	g e rtal.	
2uspaing mel (SMTP) ve	ryer.			
sistp gigslishmall.com				

Internet Mail Logon	
Type the account nam	ee and password your internet service provide har given p
Account name:	User_ID
Persword	Incoron
	Remember passgord
II your Internet service p (SPA) to access your m Authentication (SPA) of	provides requires you to use Secure Passwood Automicator all account, select the "Log On Using Secure Passwood heck box.
☐ Log on using Secur	e Password Authentication (SPA)

stemet Connec	ction Wizard				
Congratulati	iene				松
You have	successfully entered	all of the infor	nation requires	d to set up your acco	unt.
To save #	hese settings, click Fir	vish.			
			< <u>B</u> ack	Finith	Cancel
			< <u>B</u> ack	Finith	Can

- 5.1. 在「我的内送郵件伺服器 是」選擇 "POP3" 伺服器。 Choose "POP3" in "My incoming mail server".
- 5.2. 在內收郵件伺服器一欄填上
 "pop3.nwtbb.com"。在外送
 郵件伺服器一欄填上
 "smtp.nwtbb.com"。之後按
 「下一步」。

Enter "pop3.nwtbb.com" in "Incoming mail server" and enter "smtp.nwtbb.com" in "Outgoing mail server". Then press "Next".

6.1. 「帳號」已顯示你的使用者 名稱,如沒有,請輸入你的 「使用者名稱」並輸入你 的「密碼」之後按「下一 步」。

Your user name should have been displayed in "Account Name". If not, enter your "User ID" and your password. Then press "Next".

7.1. 按「完成」離開。之後請重 新啟動 Outlook Express。 Press "Finish" and then restart Outlook Express



8.

			_1
Account	Туре	Connection	<u>R</u> emove
Pop3.nwtb.com	mail (default)	Any Available	Properties
			Set as <u>D</u> efaul
			Import
			Export
			Set Order

General	0014013	Conne	ction Secur	(y Auvand	iea l
Server	Information)		_	
<u>M</u> y ir	ncoming ma	ail serve	risa (POP3	serve	r.
Inco	ming mail (l	POP3):	pop3.nwtb.	com	
Outg	oing mail (SMTP):	smtp.nwtb.c	om	
Incomir	ng Mail Ser	ver			
Ageo	ount name:		User_ID		
Pass	word:				
				er pass <u>w</u> ore	ł
ΓL	.og on usin	ig <u>S</u> ecui	e Password A	uthenticatio	'n
Outgoir	ng Mail Ser	ver —			
V N	ly server n	equires	authentication		S <u>e</u> ttings.
-					

- 8.1. 在工具列打開「工具」並選 擇「帳號」 Click on pull-down menu "Tools", then select "Accounts".
- 8.2. 在「Internet 帳號」選擇 「pop3.nwtb.com」並選擇 「內客」

Click on "Internet Accounts" tab and then select "pop3.nwtb.com" and click "properties".

9.1. 並選擇「伺服器」頁並剔取 「我的伺服器需要認證」 Click on "Servers" tab and tick "My server requires authentication"



(VI) 如何透過 HKBN Broadband Mail 網上電郵服務接收電子郵件 How to Check E-mail via HKBN Broadband Mail Web-based E-mail Account?

- 1. 進入 http://ecs.hkbnes.net。
- 2. Go to http://ecs.hkbnes.net.
- 3. 於「網上電郵」選項中輸入「登入名稱」、「電郵域名」及密碼...。 Enter "Username", "Email domain" and "password" in webmail box.
- 4. 按「遞交」[。] Click "Submit".

多謝您使用香港寬頻商業寬頻服務安裝指南!現在您可享用我們為您提供的新一代互聯網服務。

Thank you for using this HKBN Broadband Service User Guide! You can now experience our HKBN Business Broadband Service.

如有任何查詢, 歡迎致電商業客戶服務熱線或電郵至: cscorp@hkbnes.net

Should you have any further queries, please feel free to call our Corporate Customer Services Hotline or email to : <u>cscorp@hkbnes.net</u>.

商業客戶服務熱線 Business Customer Services Hotline: 128 180

24 小時維修服務熱線 24-Hour Fault Reporting Hotline: 2131 2131

<u>香港寬頻商業寬頻網址 HKBN Business Broadband Website :</u> <u>http://hkbnes.net</u>